

# UPS Real-Time Shipping Rate Module for ECWZ ASP Cart v1.x

Thank you for purchasing the UPS module v1.x for ECWZ Classic ASP Cart.

UPS Real-Time Shipping Module is a module that allows your online store to grab the shipping rate from UPS during the checkout process (real-time).

This documentation contains installation instruction and Operational manual for you to install and operate with the UPS Real-Time Shipping Rate module.

Note:

a. If you are sending irregular shaped or oversized product, the real-time shipping rate might be different than the rate you will be charged with by UPS. To find out whether your packages might fall into the irregular shaped or oversize package category, you should submit couple test order and compare with the returned rates.

b. If you need to register for UPS account, you can either register it at <http://www.ecwz.net> (under the account management section), or register at UPS.com.

## **Installation Instruction:**

### **1. Unzip the UPS\_realtime v1.x.zip and upload the unzipped files to the web server.**

After you have downloaded the UPS\_realtime v1.x.zip file from ECWZ.net, you will need to unzip this set of file into your local hard-drive. Here are the folder lists after the decompression of the zip file:

- a. /admin
- b. /store

Upload all the contents to the root of your site using any protocol you want (we recommend FTP protocol here). If you plan to put your store under your domain <http://www.mystore.com>, then you must upload all the files into the web root folder of mystore.com.

Note: If you have purchased any of the skin template set, then the skin template set should include the skin files for this module already. If your skin file set does not include files for this module, contact us at ECWZ.NET and we will email you a set of the files for the skins you have purchased.

## 2. Executing the sql.txt file to install the module into your store.

After uploading files into your web root, you need to execute the SQL statements in the sql.txt file in order to install the modules into your online store. You can use any text editor to open the SQL.txt file and execute those statements with any kind of database management tool. Keep in mind that some DB Management tool might have problem executing the “GO” keyword. If that’s the case, you might have to execute these statements one by one.

## 3. Recreate your language profile.

After you run the SQL statements, there will be new entries for the language text stored into your textlayertbl table. In order for your online store to load these new languages text, you will need to log into the back-end admin of your store -> Store Configuration -> Edit Language -> and click on the Process button to recreate the text layer file (Feel free to edit the text information for this module).

## 4. Back-end Configuration for UPS Real-Time Shipping Rate module.

### 4-1. module\_UPS\_realtime.asp

- a. UPS Account ID:** This setting stores the account ID for your UPS account.
- b. UPS Account Password:** This setting stores the account password for your UPS account.
- c. UPS Access Key:** You need to contact UPS to obtain this access key in order to communicate with UPS real-time shipping rate server..
- d. Shipping Method Status:** You can enable/disable UPS real-time shipping rate shipping method with this setting.
- e. Country Code:** This field stores the ISO country code where the online store locates. For more information about ISO country code, you can check with the following URL:  
  
<http://www.iso.org/iso/en/prods-services/iso3166ma/02iso-3166-code-lists/list-en1.html>
- f. Zip Code:** This setting stores the zip code where the online store locates.
- g. UPS Service:** This setting display the type of services this online store wants to offer to their customers.
- h. UPS Pickup Type:** This setting stores the pick-up type of packages for this online store.

**i. UPS Package Type:** This setting stores the package type from your line store.

**j. UPS Weight Type::** This setting stores the weight type (unit) for the packages that this online store would be sending out.

**k. Address Type:** This setting tells UPS where the package is sending to a residential address or personal address.

## 5. Script Editing

In order to install the UPS Real-Time shipping module, there are two script-editing you need to do. First, use any html editor or text editor and open the following file:

Storeroot/store/includes/shippingbuilder.asp

1. At the first line, (before the <% tag), add the following line:

```
<!--#include file="../moduleclass/ups_class.asp"-->
```

2. Go to line 83 (after the comment of “using real-time shipping module”) add the following code:

```
'UPS shipping  
  
if shippingRS("smethodmode") = 3 then  
  
    myreqoption=0  
  
    myshippingString = myshippingString &  
    UPSrates(session("szip"),session("scountry"),mytotalweight, shippingcount)  
  
end if
```

Once you done, just click on save and re-upload this file to overwrite the existing file.

## 6. License Information

For any questions in regards to the open-source license of this module, please contact ECWZ.NET for the licensing information.

## 7. Support Issue

For any support request/issue, please visit ECWZ, Inc’s support page at <http://www.ecwz.net/corporate/support.asp>.